TRADER DALE'S VWAP QUICK GUIDE

Contents

Installation 2

Licensing ..... **Error! Bookmark not defined.**

Setting up TD's VWAP 5

Contact 8

Installation

- Run **TraderDaleVWAPInstaller**
- If you don't have .NET Framework installed, you will get this message:



- Press Yes and proceed with the . NET framework installation
- If you are having problems with this step, simply send me an email to: contact@trader-dale.com and I will provide you with another simple solution.
- With .NET Framework installation finished (or if you don't get asked to install it), proceed with the VWAP installation:
- Press Next and go to the next step



- You will get asked to select Folder for your installation. It doesn't matter which folder you select. Nothing will get installed there. Press **Next** to proceed.



- Press **Next** again to install TD VWAP. At this step your Windows firewall could ask you if you want this program to make changes to your computer. Answer: “Yes“



- After that your installation will be finished and you can close the installer.



- Start your NinjaTrader 8 platform (if you had it running during the installation process you need to re-start it).

Licensing

After you have made your purchase you will need to send me your unique **Machine ID**. I will use it to authorize your computer to use the indicator.

To learn your Machine ID go to your NinjaTrader **Control Panel** and press **Help → 3rd Party Licensing...**



Input Vendor name and User defined ID:

- **Vendor name:** this needs to say **TraderDale**
- **User defined ID:** use your name or nickname. IMPORTANT: Avoid numbers and special characters.



Press **Submit**

This will create your unique Machine ID. Copy it and send it to my email: contact@trader-dale.com

After that, I will authorize your computer to use the indicator. This could take few minutes, few hours, but usualy no more than one working day. I will let you know via email when your computer has been enabled to use the indicator.

Setting up TD's VWAP

- Create a new chart or use an existing one. Right click the chart area and go to "Indicators"



- Find the "**TD's VWAP**" in the indicator list and press "**add**".



- The indicator is set to default settings. You can change your settings by selecting the indicator and adjusting it's Properties. **Only change Global Parameters, VWAP, 1st Deviation, and 2nd Deviation** settings. Don't change settings in Data Series, Set up, and Visual.



Global Parameters:

- **Calculation Period:** Select a period in which you want VWAP calculated
  - **Daily:** Every day a new VWAP gets printed. Recommended for Intraday trading.
  - **Weekly:** Every Week a new VWAP gets printed. Recommended for Intraday trading.
  - **Monthly:** Every Month a new VWAP gets printed. Recommended for Swing trading.
  - **Yearly:** Every Year a new VWAP gets printed. Recommended for Swing trading.

- **Data Period, Period Value:** Determines how often VWAP gets new data to be calculated. I recommend having 1 Minute for Daily and Weekly Calculation period, and 5-10 minute for Monthly and Yearly.

VWAP

- All settings are just visual. You can adjust them as you like.
- **Show Previous Session End:** shows a line, where VWAP closed in the previous session.

1st Deviation

- All settings are just visual. You can adjust them as you like.
- **Show Previous Session End:** shows a line, where 1st VWAP Deviation closed in the previous session.

2nd Deviation

- All settings are just visual. You can adjust them as you like.
- **Show Previous Session End:** shows a line, where 2nd VWAP Deviation closed in the previous session.

You can save you preffered settings as a template by hitting the "**template**" button.



Contact

If you have any questions, please contact me at: contact@trader-dale.com

Happy trading,

-Dale